



800 West Metro Parkway, Rochester, NY 14623

Tel: (585) 475-9555 Fax: (585) 475-9645

Version	Name	Date	Comment
0.0	Viewpoint Systems	12/7/2012	Original
0.1	E. Metzler	5/23/14	TSVN 1.8 updates

READ THIS BOX

Copyright © 2014, Viewpoint Systems, Inc. All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are not permitted.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT HOLDER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

We do intend to make this product as robust as make sense for us, so any feedback on issues would be appreciated. Please send comments and questions to tsvnsupport@viewpointusa.com.

Viewpoint TSVN Toolkit Installation Guide

TortoiseSVN Source Control for LabVIEW®

1 Description

The TSVN Toolbar provides seamless integration to TortoiseSVN from LabVIEW with access to TortoiseSVN commands Get lock, Commit, Update, Add, Break lock and more.

2 System Requirements

Operating System	Windows 7 or later 32 or 64-bit
TortoiseSVN	1.8.x 32 or 64-bit
LabVIEW	2012 or later (64-bit not yet supported)

* The toolbar has not been fully tested with all toolkits available for use with LabVIEW.

2.1 TortoiseSVN 1.8

TSVN Toolbar uses TortoiseSVN to perform various operations. TortoiseSVN 1.8.x must be installed and any working copies must be updated to version 1.8 before being able to use the toolbar.

The latest version of TortoiseSVN can be downloaded from <http://tortoisesvn.net/downloads.html>.

The installed version of TortoiseSVN can be found in the TSVN About window by right-clicking any file or folder in Windows Explorer and choosing **TortoiseSVN >> About** from the context menu.




Figure 1 - TortoiseSVN Context Menu



Figure 2 - TortoiseSVN About

2.1.1 TortoiseSVN Help

If you are unfamiliar with TortoiseSVN, you can use the TortoiseSVN help in the context menu or online at http://tortoisesvn.net/docs/release/TortoiseSVN_en/tsvn-quick-start.html.

2.1.2 Upgrading Working Copies

If you are upgrading from TortoiseSVN 1.8 see the help on upgrading your working copies at http://tortoisesvn.net/tsvn_1.8_releasenotes.html.

3 Installing the Toolkit

3.1 VI Package Manager

VI Package Manager (free) is used to install the toolbar and can be downloaded from <http://iki.net/vipm>.

Open the latest Viewpoint TSVN Toolkit .vip file in VIPM or double click the .vip file. Select the LabVIEW version to install the toolbar in at the top of the VIPM window. Click the install (or upgrade) button.




Figure 3: Install Screen

3.3 License Agreement




Figure 6: License Screen

3.4 Installation

If there is a problem with the install, click the **Error Details** button to find out more about the error.

